



DECUS

PROGRAM LIBRARY

DECUS NO.	8-753
TITLE	OS/8 SYSTEM OUTPUT HANDLERS,V4
AUTHOR	G. Chase
COMPANY	Portsmouth Abbey School Portsmouth, Rhode Island
DATE	February 1976
SOURCE LANGUAGE	PAL8

ATTENTION

This is a USER program. Other than requiring that it conform to submittal and review standards, no quality control has been imposed upon this program by DECUS.

The DECUS Program Library is a clearing house only; it does not generate or test programs. No warranty, express or implied, is made by the contributor, Digital Equipment Computer Users Society or Digital Equipment Corporation as to the accuracy or functioning of the program or related material, and no responsibility is assumed by these parties in connection therewith.

PROGRAM REVISION

A. GENERAL INFORMATION

Object Computer(s) PDP-8 Source Computer (if different) _____
Original File Name and Title OS/8 System Output Handlers DECUS or DEC No. 8-753
New File Name and Title (if different) _____
Original Author G. Chase
Revising Author G. Chase
Affiliation Portsmouth Abbey School
Address Portsmouth, Rhode Island

Country _____
Category Utility Source Language PAL8
Monitor/Operating System OS/8 DEC No. _____
Core Storage Required _____ Starting Address _____
Peripherals Required _____
Other Software Required _____ DEC or DECUS No. _____
Restrictions, Deficiencies, Problems _____

B. REASON(s) FOR REVISION

- | | |
|--|--|
| 1. Debug, correct known problem <input type="checkbox"/> | 4. Increased operational efficiency <input checked="" type="checkbox"/> |
| 2. Extend to handle new or different configurations <input type="checkbox"/> | 5. Operate on different processor <input type="checkbox"/> Specify _____ |
| 3. Operate under different monitor or new system <input type="checkbox"/> | 6. Other (please specify) _____ |

C. TAPES AVAILABLE

Paper Tapes ☐ Object Binary ☒ Binary Patch ☐ Object ASCII ☐ Source ☐ Other _____
DECtape ☒ LINtape ☐ Format _____ Magtape: 7 Track ☐ 9 Track ☐ BPI _____
Object Files ☒ Source Files ☒ Documentation Files ☐ Other SAV

D. ABSTRACT

These handlers simulate (LT, T4) line-printer output on a teletype or equivalent terminal. LPT was written to handle an actual line-printer, or -- especially -- matrix printers such as the Centronics LS8E.

"LT" Output Handlers (version 4) for OS-8

These handlers simulate (LT, T4) line-printer output on a Teletype or equivalent terminal. LPT was written to handle an actual line printer, or -- especially -- matrix printers such as the Centronics LS8-E.

Common to all handlers in this group:

1. The attempt to print a character beyond the specified margin width generates CR/LF/Tab, and then the character.
2. The attempt to print more than 60 lines on one page, without any form feed, causes an automatic Form (page ejection) to 11 inches length.
3. Form is also generated by (a) code 14 or 214 (b) initialization of the handler (Block 0 write) (c) Ctrl/Z (end of file). The user may also cause a 0-record write to be interpreted as end-of-file, as explained later.
4. After Form, programmed or internally generated, Line Feed and Form become null until some printing character (240-372) has been read.
5. Escape (233) is converted to \$. So is true Alt Mode (375), but the user can change this.
6. Codes 373,374,376,377 are null (this can be changed); also all control codes that are not specially handled. The "specials" are:
7. CR: echoed literally; LF: produces one line feed unless inhibited (see #4.) or unless it is the 60th line feed (see #2.). Horizontal Tab is expanded (up to 8 spaces). Vertical Tab inserts 2 blank lines. Form is discussed above; likewise Escape.
8. The handlers listen for Ctrl/C, Ctrl/O, Ctrl/S, and Ctrl/Q or any other "bland" character. Ctrl/S (stop, let me read the output) is undone by typing anything other than the first 3 mentioned above.
9. LT: and LPT: listen to the console keyboard. T4: listens to the console keyboard for Ctrl/C, to its own keyboard (device 40) for Ctrl/C, /O, /S, and /Q or equivalent. T4: prints on device 41, the usual code for a second terminal. LPT: prints on device 66.
10. Initial margin (paper width) values, ALTERable by BUILD.SV, are LT: 72 decimal, T4: 72, LPT: 80. LT: and T4: keep minus margin in location MWIDTH, LPT: keeps plus margin in MARGIN.
11. Special coding (removable) handles the Ctrl/N double-width option of Centronics printers (LPT: handler only).
12. Files: LTV4.PA and .BN; T4V4.PA and .BN; LPTV4.PA and .BN. Assembling T4V4.PA and LPTV4.PA will give "RD" messages from PAL8 (non-fatal).

13. Ctrl/O skips to the next output buffer load. I use it to move down a listing until the part I want is printed. The 11" page size is not disturbed.

re: TYP441.SV. This is not a handler, just a simple program with no particular merit. It accepts one input file and passes it on to printer 04 (console) and 41 simultaneously. If /F is included in the Command Decoder input, Form codes are expanded; otherwise they are null. SAVE options are ;200=2401. Use: multiple copies of notices, calendars, Snoopys, etc.

User Alterations and Options

1. Undo the conversion of Alt Mode to \$ sign.
2. Enable printing of other codes above 372 (172).
3. Treat a 0-record write as end-of-file.
4. Change margin (paper) width value.
5. Change default ejection (Form) from decimal 60 lines to..
6. Restrict first ejection to 3", not 11" [roll-paper users only].
- ✓7. Take out the Ctrl/N coding for LS8E double-width chars. [LPT: only].
8. Add a null to every carriage return, either
 - (a) to help "bounce" or dashpot problems, or
 - (b) to handle "raw" CR's not followed by a line feed.

How to Make Them

Consult the enclosed symbol tables. See note on "relative" addresses and "generic" names. Example: convert LT: margin to decimal 80,

.R BUILD	[decimal 72 = + 110 = -7670
\$AL TT8E,351	" 80 = + 120 = -7660
7670/ 7660 (return)	" 120 = + 170 = -7610]
\$BO	

1. ALter ALTMOD from 53xx to 7000 (NOP)
 2. ALter ALTMOD+4 from 53yy to 7000
 3. ALter NULL from 52zz to 7410 (SKP)
 - 4a. ALter MWIDTH from 7670 to minus octal margin (see above) LT:,T4:
 - 4b. ALter MARGIN from 0120 to plus octal margin LPT: only
 5. ALter VEJECT from 7704 to minus no. of printed lines per page
 6. ALter LINCTR from 7704 to 7764
 - ✓7. ALter CTRLN from 7440 to 7000 LPT: only
 8. ALter TIMING from 7000 to JMS TYPE = 4326 or 4333
- (Location TIMING-1 contains JMS TYPE for the particular handler.
You can look at this code with the EXamine command in BUILD.)

Changes from earlier versions include Ctrl/S & Q, the handling of Escape, Alt Mode and Ctrl/N in the text, recoding and reformatting of listing, explicit symbol table and ALter instructions in write-up.

COMBINED SYMBOL TABLES:

"LT:"		"T4:"		"LPT:"	
ALTMOD 0275		ALTMOD 0276		ALTMOD 0275	
BUFADR 0201		BUFADR 0201		BUFADR 0201	
CR 0446		CR 0446		CR 0457	
CTR2 0550		CTR2 0552		CTRLN 0402	
DCB 0005		DCB 0005		CTR2 0555	
DOLLAR 0340		DOLLAR 0337		DCB 0005	
ENTRY 0203		ENTRY 0203		DOLLAR 0340	
EXIT 0263		EXIT 0264		ENTRY 0203	
EXITF 0266		EXITF 0267		EXIT 0263	
EXITO 0346		EXITO 0345		EXITF 0266	
EXITR 0342		EXITR 0341		EXITO 0346	
EXITO 0343		EXITO 0342		EXITR 0342	
FORM 0470		FORM 0470		EXITO 0343	
FORMFL 0546		FORMFL 0550		FORM 0504	
LF 0454		LF 0454		FORMFL 0553	
LINCTR 0545		LINCTR 0547		LF 0470	
LOOPR 0241		LOOPR 0242		LINCTR 0552	
MARGIN 0110 (*P)		MARGIN 0110 (*P)		LOOPR 0241	
MWIDTH 0551		MWIDTH 0553		MARGIN 0557 = ADRS.	
NOFORM 0510		NOFORM 0510		MWIDTH 0556	
				NOFORM 0515	
NPRINT 0444		NPRINT 0444		NOTUPN 0412	
NULL 0345		NULL 0344		NPRINT 0455	
OUTPTR 0205		OUTPTR 0206		NULL 0345	
OUTPUT 0400		OUTPUT 0400		OUTPTR 0205	
PRINT 0271		PRINT 0272		OUTPUT 0400	
RECCTR 0200		RECCTR 0200		PRINT 0271	
RECFLD 0240		RECFLD 0241		RECCTR 0200	
RETFLD 0264		RETFLD 0265		RECFLD 0240	
SKIPIT 0313		SKIPIT 0314		RETFLD 0264	
STASH 0547		STASH 0551		SKIPIT 0313	
TAB 0513		TAB 0513		STASH 0554	
TABCTR 0544		TABCTR 0546		TAB 0520	
THIRD 0202		THIRD 0202		TABCTR 0551	
TIMING 0451		TIMING 0451		THIRD 0202	
TYPE 0526		TYPE 0526		TIMING 0462	
VEJECT 0553		VEJECT 0555		TYPE 0533	
VPAGEL 0552		VPAGEL 0554		VEJECT 0560	

(*P) = PARAMETER VALUE. N O T AN ADDRESS.

ALL R E L A T I V E ADDRESSES = THE ABOVE VALUES - 200 (OCTAL)

'ALTER' & 'EXAMINE' (BUILD.SV) WANT (1.) RELATIVE ADDRESSES, AND
(2.) GENERIC NAMES: "TT8E", "TT41", "LS8E" RESPECTIVELY.

To change DUE - from 66 to 15

RUN S4S Build

AL LS8E, 334
6666/6156

AL LS8E, 335
6666/6151

Proctor
S4S Build

