


PROGRAM LIBRARY

10	
DECUS NO.	8-469
TITLE	TOP SECRET
AUTHOR	Geoffrey Chase
COMPANY	Portsmouth Abbey School Portsmouth, Rhode Island
DATE	May 24, 1971
SOURCELANGUAGE	PAL III

Although this program has been tested by the contributor, no warranty, express or implied, is made by the contributor, Digital Equipment Computer Users Society or Digital Equipment Corporation as to the accuracy or functioning of the program or related program material, and no responsibility is assumed by these parties in connection therewith.



DECUS Program Library Write-up

**DECUS NO. 8-469** 

## "TOP SECRET"

## Encoding-Decoding Routine

Requirements: PDP-8, 4K; program occupies about 1/2 page of core, starting at address 4000.

This routine accepts characters from the keyboard of an ASR-33 and responds by typing a ciphered version of the input text. The cipher is based on a cycling counter, like the World War II Japanese naval code, so that the code cannot be broken by counting the frequency of occurence of the characters. ASCII codes below 240 (space) are not enciphered, and hence do not change the counter. ASCII codes above 332 (letter Z) are illegal as input in a plain-language text, though they appear rather frequently in the ciphered text.

Since the cycling counter must be set properly before encoding or decoding, it is necessary to halt the computer and restart at 4000 before each use. The routine is symmetrical and acts both as encoder and decoder.

## ASCII characters, by code:

Codes below 212, and also code 214, are echoed on the tape punch (if it is on) as typed. Examples: binary leader/trailer (200), tab, bell, form feed. These make suitable trailers for paper tape.

Code 212 (line feed): ignored.

Code 215 (return): echoed as a carriage return/line feed pair.

Codes 240 (space) through 332 (letter Z): enciphered and typed.

Codes 332 and up: illegal as input in plain-language text. Note: left bracket = SHIFT/K, backslash = SHIFT/L, right bracket = SHIFT/M.

Uses: (a) pure amusement

- (b) as a demonstration of the fact that an on-line Teletype is not a typewriter; it will print what the computer tells it to print, which may or may not be what the user types
- (c) as a simple example of input-output programming and of program branching, for students of machine language

/CIPHER PROGRAM; ALSO DECIPHERS CODED TEXT.
/BEFORE EACH USE (WHETHER AS ENCODER OR DE/CODER) HALT COMPUTER; LOAD ADDRESS = 4000;
/START.

## \*4000

4000	6032		KCC		
4001	6046		TLS		/INITIALIZE PRINTER
4002	3262		DCA	CTR	
4003	4244		JMS	CRLF	
	6031	G0,	KSF		
	5204	Sec. 1	JMP	1	
4006	6036		KRB		
4007	1261		TAD	M212	
4010	7450		SNA		/TRAPS OUT LINE FEED
	5204		JMP	GO	
	1257		TAD		
	7450		SNA		
	4244			CRLF	/ECHOES RETURN (215)
	7450		SNA		
	5204		JMP	GO	
4017				M23	/PRINT CODE<240 AS IS
	7510		SPA		
	5233			ECHO	
	7041		CIA		PRINTING CHARACTERS ONLY
	1256			K332	/SUBTRACT CHARACTER, MINUS 240,
4020	1200				/FROM "Z" + COUNTER
4024	1262		TAD	CTR	
	4236			PRINT	ALTERED CHARACTER
	4230			CTR	
	1252		TAD		
	0252		AND		
4030				CTR	/CTR CYCLES Ø, 3, 2, 1
4031			JMP		
4032	5204		OTTP	00	
4000	1055	FCUO	TAD	K240	
4033	1255	ECHO,		PRINT	/ORIGINAL ASCII VALUE
4034	4236		JMP		VUIDINHE ADVII VALUE
4035	5204			90	
4036	0000	PRINT,	Ø		
4037	6041		TSF		
4040	5237		-	+-1	
4041	6046		TLS		
4042	7200		CLA		
4043	5636		JMP	I PRINT	
4044	0000	CRLF,	Ø		
4045	1254	ULLEF F		K215	
4045	4236			PRINT	
4047	1253			K212	
4050	4236			PRINT	
4050	5644			I CRLF	
40.31	3044		Ortr	- Other	

2

		/ CONSTANTS
40.52	0003	K3, 3
. 4053	0212	K212, 212
4054	Ø215	K215, 215
4055	0240	K240, 240
40.56	Ø332	K332, 332
4057	7775	M3, -3
4060	7755	M23, -23
4061	7566	M212,-212
4062	0000	CTR, Ø
		/ HALT FROM CONSOLE
CRLF	4044	
CTR	4062	4
ECHO	4033	
GO	4004	
K212	4053	
K215	4054	
K240	4055	
K3	4052	
K332	4056	
M212	4061	
M23	4060	
M3	4057	
PRINT	4036	
B000&2		
	1.	<(*
		/<("\$<(*
		0=+8!
		•
		2"
		2
		**2*

?=?-=63

-\*\*\*0!\*0&: .

.

+\*\* . 5

